	DDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDD	
--	--	--

EXE

		*** *** *** *** *** *** *** *** *** **	PPPPPPPPPPPPPPPPPPPPPPPPPPPPPPPPPPPPPP	AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA	HH H	DDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDD	
	\$						

```
EDTSTITYPAHD
V04-000
                       EDT$TITYPAHD - check for type ahead EDT$$TI_TSTTYAHED - check for type ahead
                                                                                                                               VAX-11 Bliss-32 V4.0-742 Page DISK$VMSMASTER:[EDT.SRC]TITYPAHD.BLI;1
                                  "SBTTL 'EDT$$TI_TSTTYAHED - check for type ahead'
                      GLOBAL ROUTINE EDT$$TI_TSTTYAHED
                                                                                                        ! Check for type ahead
                                     FUNCTIONAL DESCRIPTION:
                                              This routine checks to see if a character was typed ahead. If we are in recovery mode, always return false. If the type-ahead counter is greater than 0, return true, and if not, try to read a type-ahead character and if it is read, place it in the type-ahead buffer and return true.
                                     FORMAL PARAMETERS:
                                              NONE
                                     IMPLICIT INPUTS:
                                              EDT$$G_RCOV_MOD
EDT$$G_RDAHED
                                     IMPLICIT OUTPUTS:
                                              EDT$$G_RDAHED
EDT$$T_RDAHED
                                     ROUTINE VALUE:
                                              0 = no type ahead
                                              1 = there was type ahead
                                     SIDE EFFECTS:
   118
                                              NONE
    120
121
123
123
124
127
128
133
133
133
133
133
134
141
                                        BEGIN
                                        EXTERNAL ROUTINE
                                              EDT$$TI_RDTYAHED;
                                        EXTERNAL
                                              EDT$$G_RCOV_MOD,
EDT$$G_RDAHED,
                                                                                                           Recovery mode flag
                                                                                                          Type ahead counter
                                                                                                        ! Text from type-ahead
                                              EDT$$T_RDAHED;
                                        IF .EDT$$G_RCOV_MOD THEN RETURN (0);
                                        IF (.EDT$$G_RDAHED GTR 0) THEN RETURN (1);
                                        EDT$$G_RDAHED = EDT$$TI_RDTYAHED (EDT$$T_RDAHED);
                                        IF (.EDT$$G_RDAHED GTR 0) THEN RETURN (1) ELSE RETURN (0);
                                        END:
                                                                                                        ! of routine EDT$$TI_TSTTYAHD
```

EDTSTITYPAHD	EDTSTITYPAND - check for EDTSSTI_TSTTYAHED - c	or type ahead heck for type ahead	L 11 16-Sep-1 14-Sep-1	984 01:57:01 984 12:24:59	VAX-11 Bliss-32 V4.0-742 DISK\$VMSMASTER:[EDT.SRC]TITYPA	Page 4 HD.BLI;1 (3)
	00000000G	52 0000000006 00 1A 000000006 00 62 12 0000000006 00 00 62 50 04 50 01	004 00000 9E 00002 E8 00009 D5 00010 14 00012 9F 00014 FB 0001A D0 00021 15 00024 D0 00026 1\$:	.IDENT \VO4 .EXTRN EDTS .EXTRN EXTRN	STITYPAHD EDTSTITYPAHD - check for d4-000\ SSTI_RDTYAHED SSG_RCOV_MOD SSG_RDAHED, EDTSST_RDAHED TSCODE,NOWRT, SHR, PIC,2 SSTI_TSTTYAHED, Save R2 SSG_RDAHED, R2 SSG_RDAHED, R2 SSG_RDAHED EDTSSTI_RDTYAHED EDTSSTI_RDTYAHED EDTSSG_RDAHED R0	: 0657 : 0703 : 0705 : 0707
		50	04 00029 D4 0002A 2\$: 04 0002C	RET CLRL RO RET		0711
; Routine Size	e: 45 bytes, Routine	Base: _EDT\$CODE +	0000			

: 142

0712 1 0713 1 !<BLF/PAGE>

EDTSTITYPAHD	EDT\$TITYPAHD - check for type ahead EDT\$\$TI_TSTTYAHED - check for type ahead	M 11 16-Sep-1984 01:57:01 14-Sep-1984 12:24:59	VAX-11 Bliss-32 V4.0-742 Page DISK\$VMSMASTER:[EDT.SRC]TITYPAHD.BLI;1 (4			
: 145 : 146 : 147	0714 1 END 0715 1 0716 0 ELUDOM	! of module EDT\$TYTYPAHD				

Attributes

PSECT SUMMARY

Name Bytes

45 NOVEC, NOWRT, RD , EXE, SHR, LCL, REL, CON, PIC, ALIGN(2)

Library Statistics

File	Total	Symbols Loaded	Percent	Pages Mapped	Processing Time
_\$255\$DUA28:[EDT.SRC]EDT.L32;1 _\$255\$DUA28:[EDT.SRC]PSECTS.L32;1	377	0	50	40	00:00.2 00:00.1

COMMAND QUALIFIERS

BLISS/CHECK=(FIELD, INITIAL, OPTIMIZE)/NOTRACEBACK/LIS=LIS\$:TITYPAHD/OBJ=OBJ\$:TITYPAHD MSRC\$:TITYPAHD.BLI/UPDATE=(ENH\$:TITY PAHD)

Size: 45 code + 0 data bytes Run Time: 00:09.4 Elapsed Time: 00:11.1

Run Time: 00:09.4; Elapsed Time: 00:11.1; Lines/CPU Min: 4560; Lexemes/CPU-Min: 12184; Memory Used: 56 pages; Compilation Complete

_EDT\$CODE

0140 AH-BT13A-SE

DIGITAL EQUIPMENT CORPORATION CONFIDENTIAL AND PROPRIETARY

